
Splitting License Plate Quick Guide 8-22-22


- When you ship a portion of a pallet (LP license plate), you must create a new LP for the product that you are shipping or removing off an existing LP. BC does not allow one LP to be shipped on multiple orders.
- General Process:
 - o It's recommended that you do a LP split before you do Shed Picks in the Warehouse Shipments.
 - Create New LP for cases you are removing and shipping off an existing pallet.
 (The original LP stays with the remaining cases on the pallet.)
 - Recommended that you have the starting LP Tag (or number written down)
 when doing this task at your computer.

OPTION 1: Splitting LP Before Warehouse Shipment and Picking


Click LP JOURNAL BATCHES




In this list your location should be showing. Click OPEN




Enter the LP/Pallet that you are splitting. Use lookup list or scan the LP.




For Sheds Using Own LPs (If using BC LP's – skip to next section below): Enter new LP
 No. in the "Target LP" field for the new pallet and enter quantity that is going to the new LP/Pallet




- When done click the POST
- To print the new LP and the revised LP go to the License Plate tile on your main screen.
 Click the tile
- Note you can also move cases from one LP to another. In this situation, you would enter an existing LP No. that you are moving cases to.




- Find the LP No. that you want to print by scanning the list or entering the number in the search function
- With the LP selected click More Options → Actions → Print LP Tag
- PROCESS COMPLETE




- For Sheds Using BC LPs:
- In the ribbon, click more options → actions → New LP
- Enter or scan source LP that is going to be split/reduced.
- Enter quantity that is going to the new LP/Pallet



- When done click the POST
- Note you can also move cases from one LP to another. In this situation, you would enter the LP No. that you are moving cases to.
- To print the new LP and the revised LP go to the License Plate tile on your main screen.
 Click the tile






- Find the LP No. that you want to print by scanning the list or entering the number in the search function
- With the LP selected click More Options → Actions → Print LP Tag
- PROCESS COMPLETE

OPTION 2: Splitting LP During Warehouse Shipment Pick Function:

- The process for this option is very similar to option 1, except that you initiate the LP split function within the Shed Pick function of the Warehouse Shipment.
- Within the Shed Pick table, click LP Journal.



- Go to Instructions above in Green For Sheds Using Own LPs
- Go to Instructions above in Yellow For Sheds Using BC LPs: